

nats-top



- [Installation](#)
- [Usage](#)
- [Options](#)
- [Commands](#)
 - [option](#)
 - [limit](#)
 - [s, ? and q Commands](#)
- [Tutorial](#)

[nats-top](#) is a [top](#)-like tool for monitoring nats-server servers.

“ ”

The `nats-top` functionality is now available in the `nats` CLI tool using the `nats top` command.

The nats-top tool provides a dynamic real-time view of a NATS server. nats-top can display a variety of system summary information about the NATS server, such as subscription, pending bytes, number of messages, and more, in real time. For example:

```
nats-top
```

```
nats-server version 0.6.4 (uptime: 31m42s)
```

```
Server:
```

```
Load: CPU: 0.8%   Memory: 5.9M   Slow Consumers: 0
```

```
In:   Msgs: 34.2K   Bytes: 3.0M   Msgs/Sec: 37.9   Bytes/Sec: 3389.7
```

```
Out:  Msgs: 68.3K   Bytes: 6.0M   Msgs/Sec: 75.8   Bytes/Sec: 6779.4
```

```
Connections: 4
```

HOST	CID	SUBS	PENDING	MSGS_TO	MSGS_FROM	BYTES_TO
BYTES_FROM	LANG	VERSION	SUBSCRIPTIONS			

127.0.0.1:56134	2	5	0	11.6K	11.6K	1.1M
905.1K	go	1.1.0	foo, hello			
127.0.1.1:56138	3	1	0	34.2K	0	3.0M
0	go	1.1.0	_INBOX.a96f3f6853616154d23d1b5072			
127.0.0.1:56144	4	5	0	11.2K	11.1K	873.5K
1.1M	go	1.1.0	foo, hello			
127.0.0.1:56151	5	8	0	11.4K	11.5K	1014.6K
1.0M	go	1.1.0	foo, hello			

Installation

nats-top can be installed using `go install`. For example:

```
go install github.com/nats-io/nats-top
```

With newer versions of Go, you will be required to use `go install github.com/nats-io/nats-top@latest`.

NOTE: You may have to run the above command as user `sudo` depending on your setup. If you receive an error that you cannot install nats-top because your `$GOPATH` is not set, when in fact it is set, use command `sudo -E go get github.com/nats-io/nats-top` to install nats-top. The `-E` flag tells sudo to preserve the current user's environment.

Usage

Once installed, nats-top can be run with the command `nats-top` and optional arguments.

```
nats-top [-s server] [-m monitor] [-n num_connections] [-d delay_in_secs] [-sort by]
```

Options

Optional arguments inclde the following:

Option	Description
<code>-m monitor</code>	Monitoring http port from nats-server.

Option	Description
<code>-n num_connections</code>	Limit the connections requested to the server (default 1024).
<code>-d delay_in_secs</code>	Screen refresh interval (default 1 second).
<code>-sort by</code>	Field to use for sorting the connections (see below).

Commands

While in nats-top view, you can use the following commands.

option

Use the `o<option>` command to set the primary sort key to the `<option>` value. The option value can be one of the following: `cid`, `subs`, `pending`, `msgs_to`, `msgs_from`, `bytes_to`, `bytes_from`, `lang`, `version`.

You can also set the sort option on the command line using the `-sort` flag. For example: `nats-top -sort bytes_to`.

limit

Use the `n<limit>` command to set the sample size of connections to request from the server.

You can also set this on the command line using the `-n num_connections` flag. For example: `nats-top -n 1`.

Note that if `n<limit>` is used in conjunction with `-sort`, the server will respect both options allowing queries such as the following: Query for the connection with largest number of subscriptions: `nats-top -n 1 -sort subs`.

s, ? and q Commands

Use the `s` command to toggle displaying connection subscriptions.

Use the `?` command to show help message with options.

Use the `q` command to quit nats-top.

Tutorial

For a walkthrough with `nats-top` check out the [tutorial](#).

- #3
- cocobook-sync

2026-10-28 11:10:56 UTC
- cocobook-sync

2026-10-29 01:42:35 UTC