Image Dimensions Control

□□

- □□ __
- □□□ __
- □□ __

Elementor image dimensions control displays a width input, a height input and an apply button. It is used by the Image Size group control to allow the user to set custom width or height for an image.

The control is defined in `Control_Image_Dimensions` class which extends `Control_Base_Multiple` class.

When using this control, the `type` should be set to `\Elementor\Controls_Manager::IMAGE_DIMENSIONS` constant.

□□

□□	□□	□□□	□□
`type`	`string`	image_dimensions	□□□□□□
`label`	`string`		□□□□□□□□□□□
`description`	`string`		□□□□□□□□□□□
`show_label`	`bool`	false	□□□□□□□
`label_block`	`bool`	true	□□□□□□□□□□□□
`separator`	`string`	default	□□□□□□□□□□□□□ □□ `default` □ `before` □ `after` □ `default` □□□□□□□□□□□□□ □□□□□□□□□ `before` / `after` □□□□□□□□□□□□ / □□□

□□	□□	□□□	□□
`default`	`array`		□□□□□□□□□ • **$width** (`int`) □□□□□ • **$height** (`int`) □□□□□

□□□

```
[
□'width' => '',
□'height' => '',
]
```

(*`array`*) □□□□□□□□□□□□□□

- **$width** (*`int`*) □□□□□
- **$height** (*`int`*) □□□□□

□□

```
<?php
class Elementor_Test_Widget extends \Elementor\Widget_Base {

□protected function register_controls(): void {

□□$this->start_controls_section(
□□□'content_section',
□□□[
□□□□'label' => esc_html__( 'Content', 'textdomain' ),
□□□□'tab' => \Elementor\Controls_Manager::TAB_CONTENT,
□□□]
□□);

□□$this->add_control(
□□□'custom_dimension',
□□□[
□□□□'label' => esc_html__( 'Image Dimension', 'textdomain' ),
```

```
□□□□'type' => \Elementor\Controls_Manager::IMAGE_DIMENSIONS,
□□□□'description' => esc_html__( 'Crop the original image size to any custom size. Set custom width or height to keep the original size ratio.', 'textdomain' ),
□□□□'default' => [
□□□□□'width' => '',
□□□□□'height' => '',
□□□□],
□□□]
□□);

□□$this->end_controls_section();

□}

}
```

□□□ #2
□ □□□ □□□ 2026-03-26 17:08:44 UTC
□ □□□ □□□ 2026-03-26 17:08:44 UTC